

subtle - Bug #236

Wifi sublet - unhandled condition

07/18/2011 04:52 AM - david unric

|                                                                                                                                      |                  |                        |            |
|--------------------------------------------------------------------------------------------------------------------------------------|------------------|------------------------|------------|
| <b>Status:</b>                                                                                                                       | Fixed            | <b>Start date:</b>     | 07/18/2011 |
| <b>Priority:</b>                                                                                                                     | Urgent           | <b>Due date:</b>       |            |
| <b>Assignee:</b>                                                                                                                     | Christoph Kappel | <b>% Done:</b>         | 0%         |
| <b>Category:</b>                                                                                                                     | Bugfix           | <b>Estimated time:</b> | 0.00 hour  |
| <b>Target version:</b>                                                                                                               | Nu               |                        |            |
| <b>Description</b>                                                                                                                   |                  |                        |            |
| Hi,                                                                                                                                  |                  |                        |            |
| just a small bug in wifi.rb on line 36 causes script to abort with unhandled exception when <i>link</i> variable is not initialized. |                  |                        |            |
| Either fix the mentioned line                                                                                                        |                  |                        |            |
| s.data = '%s%s (%d/100)' % [ s.icon, essid.strip, link ]                                                                             |                  |                        |            |
| with something like                                                                                                                  |                  |                        |            |
| s.data = '%s%s (%d/100)' % [ s.icon, essid.strip, link.nil? ? 0 : link ]                                                             |                  |                        |            |
| or directly handle fail case of '/proc/net/wireless' file parsing on line 19:                                                        |                  |                        |            |
| link, level, noise = wireless.scan(/#{s.device}:s*d*s*([0-9-]+).s+([0-9-]+).s+([0-9-]+)/).flatten                                    |                  |                        |            |

History

#1 - 07/18/2011 09:58 AM - Christoph Kappel

- Category set to Bugfix
- Status changed from Unconfirmed to Confirmed
- Assignee set to Non member users
- Target version set to Nu

What is in /proc/net/wireless when the link level is empty?

#2 - 07/18/2011 08:24 PM - Christoph Kappel

- Status changed from Confirmed to Fixed

Fixed in wifi-0.7.